

## Release Notes

v1.0	Jul 29 2014	Tiffanie Shakespeare / Katie Caldwell	Spec based off of Gallery Spec for 2.1
v1.1	Aug 20 2014	Katie Caldwell	Added Confirmation Banner Updated spec to reflect ON HOLD feature: "Saved edits" pg 11. • For 2.1 - toolbar icons do not indicate edits to previously edited image
v1.2	Sept 02 2014	Katie Caldwell	Added Filter Names Change Exposure values to -100 0 +100

### Open Issues

### July 29, 2014

Currently, saved edits create copies of an original image in Gallery. Ideally, all edits are "remembered" in a layered fashion on the Original image, saved with the original timestamp. If that is not possible, then perhaps "Save" string should be adjusted to inform the user that a "Copy" or "New" image is being saved (to a new place, with a new timestamp - not necessarily from the original album the image was initially selected from).

Edited Images will be saved as the original (with timestamp), not as duplicates (with new timestamps). Edits are "layered" on the original image and user can return image to original state, if desired.

### Update for 2.1:

djf: Aug 18, 2014

We're still editing a copy of the image. The original is never modified, and until the user clicks Save, we're regenerating the preview from the original image, so edits can be made and undone forever. We always re-generate from the original so nothing is lost. When the user clicks save, they'll get a new image, but the original is still displayed. (That may be something we want to change eventually but it is out of scope for what Punam is doing now.) None of this has changed: it is how we did it in the past and it is how we're doing it now.

### Punam: Aug 20, 2014

I see this requirement is in specs on page 11 - under EditMode- General. It says

'Multiple edit modes (ex: Crop, Filter and Auto-Enhance) can be "on" at the same time (layered). After an image is saved to the Gallery, these edits are remembered. Should the user return to edit mode (opening an edited image), all features that were applied (ex: Filter X) are highlighted within each mode.'

TBH this requirement is the trickiest one and will be difficult to implement in current scope. The way gallery works now, once user clicks save, edited image is saved as new image. AFAIK, there is no easy way to tell what are the edits applied on the new edited image once we come out of edit screen after hitting save.


## **User Stories**

Bug 1042319 - [gallery] Update gallery edit UI and Visuals

# Wireframes

# Gallery - Edit Mode: General Flow


#### 01. Gallery View



User taps thumbnail of recent image


Refer to [2.1] Gallery Views.pdf

#### 02. Single Image View



User selects "Edit icon" from toolbar

#### 03. Editor



User selects Filters Mode

"Save" is disabled (grayed out) until user makes an edit.

"X" Cancels out of Editor and returns to 02. Single Image View


After edits are made and applied, user selects Save and returns to 05. Single Image View - Saved

Modes - Left to right

Since Auto-Enhance is the only on/off toggle, and will not go to a new screen, it is recommended to place it last in the mode toolbar

Exposure, Crop, Filters, Auto-Enhance

#### 04. Mode




User selects "Apply" after selecting a filter. This takes the user back to 03. Editor

"Apply" is disabled (grayed out) until an "edit" has been made.

"X" Cancels out of Editor and returns to 03. Editor

For each mode, controls are at the bottom.

#### 05. Single Image View - Saved




Display Confirmation banner that a copy has been saved.

.....

Confirmation banner fades away after 2 seconds

### Gallery - Edit Mode: Exposure


#### 01. Editor



Modes: Exposure, Crop, Filters, Auto- Enhance

"Save" is disabled until an edit has occurred.

#### 02. Mode: Exposure




Exposure defaults to "0" center position

Dragging slider left or right adjusts image exposure. Slider ranges from a minimum value of -100 to a maximum value of 100.

"Apply" option is disabled [grayed out] until first edit has occurred.


#### 03. Editor - Exposure Applied



Exposure icon changes to enabled/On state if the original image has been edited (edits applied).

"Save" returns user to 04. Single Image View-Saved with updated image preview

#### 04. Single Image View - Saved



Display Confirmation banner that a copy has been saved. Confirmation banner fades away after 2 seconds.

#### Notes

#### **Quick Summary**

Exposure uses a slider control with 7 discrete settings. Exposure defaults to the "0" setting.

Toolbar - Edit Modes

From left to right: Exposure, Crop, Filters, Auto-Enhance. Each icon has 2 states: On/Off. Icons default to OFF, only when an edit has been "Applied" in a specific mode does the icon change to ON state. Exception: Auto-Enhance (see Gallery - Edit Mode: Auto-Enhance for details)

B Cancel

Cancels out of specific Edit mode (ignores any changes made is specific edit mode. Ex: exposure). Returns to 01. Editor screen.

Mode Adjustment: Exposure slider

Exposure uses a slider with a range of -100 to +100. Slider defaults to the center position 0. User will only see the current value of slider position.

D Apply Edits

Applies edits to original image and returns to 03. Editor screen

Saves Edit


Saves edits and updates Single Image View to reflect edits.

**Confirmation Banner** 


Displays message to user confirming saved edits and that a new copy of the image exists.

Slider Behaviour [2.2?]

User taps far left or right end points or center point, slider snaps to targets: -100 / 0 / 100




User drags the slider left or right. Exposure value updates with drag action.



## Gallery - Edit Mode: Crop


#### 01. Editor



Modes: Exposure, Crop, Filters, Auto- Enhance

"Save" is disabled until an edit has occurred.

#### 02. Mode: Crop



by default, Free Crop tool is highlighted


Scale (and animate?) image slightly from edges to avoid confusion with edge swipe gesture to change app

Have crop handles appear inside edges of image to avoid edge swipe gesture between dragging edges of crop tool and side gesture for jumping to another app

Labels have been added below crop tools

"Apply" option is disabled [grayed out] until first edit has occurred.

#### 03. Mode: Crop




Dragging handles of crop tool (corners, left/right, and top/bottom) masks original image

Selecting a specific ratio option limits the aspect ratio of cropping tool

Tapping "Original" reverts image to original, uncropped state

Should cropped area zoom in after user makes edits - so user can see greater detail/have more control over specific crop?

#### 04. Editor - with Crop



Crop icon changes to "ON" state if the original image has been cropped.


"Save" returns user to Single Image View with updated image preview with confirmation banner.

#### Notes

#### **Quick Summary**

Crop allows users to change to size of the image by masking (hiding) a portion of the original image.






Crop Handles
To avoid complication with left to right swipe gesture for navigating between apps, scale image slightly and, if possible, place crop handles INSIDE image frame.

# Gallery - Edit Mode: Filters


#### 01. Editor



Modes: Exposure, Crop, Filters, Auto- Enhance

"Save" is disabled until an edit has occurred.

#### 02. Mode: Filters



Defaults to Original highlighted in toolbar


"Apply" option is disabled [grayed out] until first edit has occurred.

Once edits have been made, "Apply" becomes active and tapping "Apply" returns to 03. Editor screen with changes to image

#### 2.2 Note:

Filter (effects) rendering require an update, strings may require change once filters are enhanced (by visual design).


#### 03. Editor - Filter Applied



Filter icon changes to "ON" state if the original image has been edited.

"Save" returns user to Single Image View with updated image preview

### 04. Single Image View - Saved



Display Confirmation banner that a copy has been saved. Confirmation banner fades away after 2 seconds.

#### Notes

#### **Quick Summary**

There are 4 preset filters, plus the option to revert to original image.




#### **Labels Added**

Add labels below each filter, including "Original" where no filter has been added. The label [strings TBD] shows the filter name so users understand what the icon does. Labels are consistent for Exposure, Crop & Filters

## Gallery - Edit Mode: Auto-Enhance


#### 01. Editor



Modes: Exposure, Crop, Filters, Auto- Enhance

"Save" is disabled until an edit has occurred.

#### 02. Enabled Auto-Enhance




The Auto-Enhance icon itself is a toggle and reflects the current state. Each time tapped, the state is toggled.

Tapping the Auto-Enhance icon displays a textual confirmation (A) and the icon changes to the ON state. Text fades out in 3 seconds.

Tapping the Auto-Enhance icon again disables the feature and a textual confirm appears "Auto-Enhance Off". Icon returns to default OFF state.

Tapping "Save" returns to Single Image View

#### 03. Single Image View - Saved



Display Confirmation banner that a copy has been saved. Confirmation banner fades away after 2 seconds.

#### Notes

#### **Quick Summary**

Auto-Enhance is 2 state edit mode. Auto-Enhance is, by default, set to OFF. Tapping the Auto-Enhance icon in the toolbar turns Auto-Enhance ON. Image will change to reflect ON state and the icon in the toolbar will reflect that an edit has been made.


### Confirmation/Display Text

The text shows the feature name so users understand what the icon does. This also shows the current state - on or off - in addition to the icon. Displays for 3 seconds after the setting (on/off) has been selected

B Toolbar Icons
Toolbar icons have 2 states: On/Off

# Gallery - Edit Mode: General


01. Editor -



When returning to an already edited image, toolbar "remembers" edits and icons indicate if a mode/feature is "On".

"Save" is disabled until an edit is made.

02. Mode: Filters



Highlights filter saved from previous edit.

"Apply" option is disabled [grayed out] until new edit has occurred.

#### Notes

#### **Quick Summary**

Multiple edit modes (ex: Crop, Filter and Auto-Enhance) can be "on" at the same time (layered). After an image is saved to the Gallery, these edits are remembered. Should the user return to edit mode (opening an edited image), all features that were applied (ex: Filter X) are highlighted within each mode.



#### **Toolbar Icons**

Toolbar icons have 2 states: On/Off. Toolbar icons reflect previous edits to edited/saved images.

# Thanks!

From your friends in Firefox OS UX